



MOST ANDROID TABLETS

If there isn't an e-mail shortcut on the home screen, tap the Apps button  (usually in the top right of screen), then tap and hold the Email icon. After a pressing it for a couple seconds, the screen will change, and you can drag the email icon to a location on the home screen.

Note: If the Account setup wizard does not appear when you tap on the e-mail icon, then you have to go to Settings, Accounts. Tap the "Add account" button to start the wizard.

Enter your e-mail address and password, then tap Next.



Account setup


Email account

You can set up email for most accounts in just a few steps.

Email address

Password

Tap "POP3" for the account type.



Account setup


Account type

What type of account is this?

POP3

IMAP

Change the pop3 server to mail.havilandtelco.com, and the security type to "SSL/TLS (accept all certificates)". Tap Next.




The screenshot shows the 'Incoming server settings' screen. At the top, there is a header 'Account setup' with an envelope icon. Below it, the title 'Incoming server settings' is displayed in green. The settings are as follows:

Username	myemail@havilandtelco.com
Password	••••••••
POP3 server	mail.havilandtelco.com
Security type	SSL/TLS (Accept all certificates)
Port	995
Delete email from server	Never

Red arrows point to the 'POP3 server' and 'Security type' fields.

Change the outgoing security type to STARTTLS (accept all certificates) and tap Next.



The screenshot shows the 'Outgoing server settings' screen. At the top, there is a header 'Account setup' with an envelope icon. Below it, the title 'Outgoing server settings' is displayed in green. The settings are as follows:

SMTP server	mail.havilandtelco.com
Security type	STARTTLS (accept all certificates)
Port	587

Below the settings, there is a checkbox labeled 'Require sign-in.' which is checked. At the bottom, there are fields for 'Username' (myemail@havilandtelco.com) and 'Password' (••••••••).

A red arrow points to the 'Security type' field.

Change the "Inbox Checking Frequency" to the value you would like. Checking more often allows you to get e-mail more quickly, but it also drains your battery faster.

Check the box to send mail from this account by default, then tap Next.

Account settings

Account options

Inbox checking frequency Every 10 minutes ←

Send email from this account by default. ←

Notify me when email arrives.

Sync email from this account.

Enter your name and tap Next.

Account setup

Your account is set up, and email is on its way!

Give this account a name (optional)

myemail@havalandtelco.com

Your name (displayed on outgoing messages)

Your Name ←

You're all done! It may take a few minutes to receive your e-mails.

Note:

This device receives 25 messages at a time. To download more, you'll have to scroll down to the bottom of the list and tap "Load More Messages".